

Steps to Deploy Model Using Edge Impulse Studio

To deploy the final optimized sign language translation model onto the Nicla Vision board using Edge Impulse, follow the steps below:

1. **Access the Public Project**

Open the Edge Impulse project titled [Portable AI-Based Sign Language Translator](#), which has been shared publicly.

2. **Open the Impulse**

Navigate to the impulse named **"Main"** within the project. This impulse includes the preprocessing, feature generation, model training, and classification blocks.

3. **Run the Full Pipeline**

Execute each block in the pipeline in sequence:

- Data preprocessing
- Feature generation
- Model training
- Model testing and evaluation

4. **Export the Final Model**

After validating the model performance:

- Go to the **Deployment** tab
- In the "Deployment Type" dropdown, select **OpenMV Library**
- Click **Build** to generate the deployment package

5. **Deploy to Nicla Vision**

Once the **.zip** deployment package is downloaded:

- Extract the contents of the archive
- Rename the **object_detection.py** file to **main.py** and copy it to the Nicla Vision
- Also copy **trained_model.tflite** and **labels.txt** to the root directory of the Nicla Vision

6. **Run the System**

- Power the Nicla Vision using USB or a battery
- The device will automatically load the model and begin detecting supported hand gestures
- Real-time translation output and detection overlays will appear on the connected interface